

Configuring Windows NT 4.0

Note: You must have Service Pack 3 installed first. For information about getting Service Pack 3, please visit <http://www.microsoft.com/>.

1. Double click on **My Computer**, then **Dial-Up Networking**.
 - a. If no entries have been created yet, click the OK button in the dial-Up Networking dialog box that appears to create a new entry. If you already have entries in your phone book, you will see the Dial-Up Phone Book. Click on the New button to create a new entry.
2. Enter the name of the phone book entry in the New Phonebook Entry Wizard. An example would be **onlinenw**.
3. Leave the **I know all about phonebook entries and would rather edit the properties directly** box unchecked, and click next.
4. Check the **I am calling the internet** option. Also check the last box, **The Non-Windows NT....**, click next.
5. Select a modem port from the list of available ports. Your modem will probably be listed by it's name. Example: Supra 56I (COM2), then click next.
6. Type in the phone number: **503-472-5920**, click next.
7. Click **Finish** to end the wizard and bring up the Dial-Up Networking Box.

TO EDIT A DIALUP NETWORKING ENTRY

1. Open Dial-Up networking. The dial-up networking box appears.
2. Select an entry from the Phonebook Entry to dial combo box, and lick the More button. This pops up a list of options. Select Edit Entry and Modem Properties to show the Edit Phonebook entry dialog box. The first tab is called the **Basic** tab.
3. In the Entry Name box, type in **OnlineNW** if isn't already there. Make sure the phone number is **503-472-5920**. In the Dial-Using box, double check to make sure your modem is listed.
4. Click on the Server tab up at the top of this window. In type of Dial-Up server make sure it is set to **PPP: Windows NT, Windows 95, Internet**. In the Network Protocols box, only **TCP/IP** should be checked.
5. Click on the **TCP/IP Settings** button. Under this new window, the option at the top should be set to **Server assigned IP address**. The next section down, select **Specify name server addresses**. In the Primary DNS box, type in **204.200.26.2**. In the secondary DNS box, type in **198.92.64.230**. The two boxes at the bottom of this windows should both be checked.
6. Close all screens, then restart Windows NT.
7. After NT has fully rebooted, go to Dial-Up networking. Click on Phonebook Entry to Dial, and select OnlineNW. Click dial. Enter your username and password, then click connect.